

NAME

vnStat image output – png image output support for vnStat

SYNOPSIS

```
vnstati [ -cdhimostv? ] [ -i interface ] [ --hours ] [ --days ] [ --months ] [ --top10 ] [ --summary ]
[ -hs ] [ --hsummary ] [ -vs ] [ --vsummary ] [ -ne ] [ --noedge ] [ -nh ] [ --noheader ] [ -ru ] [
--rateunit ] [ --output file ] [ --cache time ] [ --iface interface ] [ --config file ] [ --dbdir directory
] [ --locale locale ] [ --help ] [ --version ]
```

DESCRIPTION

The purpose of **vnstati** is to provide image output support for statistics collected using **vnstat(1)**. The image file format is limited to png. All basic outputs of vnStat are supported excluding live traffic features. The image can be outputted either to a file or to standard output.

OPTIONS

- s, --summary**
Output traffic summary.
- hs, --hsummary**
Output traffic summary including hourly data using a horizontal layout.
- vs, --vsummary**
Output traffic summary including hourly data using a vertical layout.
- d, --days**
Output traffic for days.
- h, --hours**
Output traffic for the last 24 hours.
- m, --months**
Output traffic for months.
- t, --top10**
Output all time top10 traffic days.
- ne, --noedge**
Remove darker edges from around the image.
- nh, --noheader**
Remove header containing title and update time. Time of the previous update will still be visible in the lower right corner using a less visible color.
- ru, --rateunit**
Swap the configured rate unit. If rate has been configured to be shown in bytes then rate will be shown in bits if this option is present. In the same way, if rate has been configured to be shown in bits then rate will be shown in bytes when this option is present.
- o, --output *file***
Write png image to *file* and exit. Output can be directed to stdout by giving "-" as filename.
- c, --cache *time***
Update output file only if at least *time* minutes have passed since the previous file update. This option is ignored if stdout is used as output.
- i, --iface *interface***
Use *interface* instead of default or configured interface.
- config *file***
Use *file* as config file instead of using normal config file search function.
- dbdir *directory***
Use *directory* as database directory instead of using the directory specified in the configuration file or the hardcoded default if no configuration file is available.

--locale *locale*

Use *locale* instead of using the locale setting specified in the configuration file or the system default if no configuration file is available.

-, --help

Show a command summary.

-v, --version

Show current version.

FILES

/var/lib/vnstat/

Default database directory. Files are named according to the monitored interfaces.

/etc/vnstat.conf

Config file that will be used unless *\$HOME/.vnstatrc* exists. See **vnstat.conf(5)** for more information.

EXAMPLES

vnstati -s -i eth0 -o /tmp/vnstat.png

Output traffic summary for interface eth0 to file /tmp/vnstat.png.

vnstati -vs -i eth0+eth1+eth2 -o /tmp/vnstat.png

Output traffic summary with hourly data under the normal summary for a merge of interfaces eth0, eth1 and eth2 to file /tmp/vnstat.png.

vnstati -h -c 15 -o /tmp/vnstat_h.png

Output hourly traffic statistics for default interface to file /tmp/vnstat_h.png if the file has not been updated within the last 15 minutes.

vnstati -d -ne -nh -o -

Output daily traffic statistics without displaying the header section and edges for default interface to standard output (stdout).

vnstati -m --config /home/me/vnstat.cfg -i -o -

Output monthly traffic statistics for default interface specified in configuration file /home/me/vnstat.cfg to standard output (stdout).

AUTHOR

Teemu Toivola <tst at iki dot fi>

SEE ALSO

vnstat(1), **vnstatd(1)**, **vnstat.conf(5)**, **units(7)**