NAME

vnStat image output - png image output support for vnStat

SYNOPSIS

```
vnstati [ -cdhimostv? ] [ --cache time ] [ --config file ] [ --days ] [ --dbdir directory ] [ --help ] [
--hours ] [ -hs ] [ --hsummary ] [ -i interface ] [ --iface interface ] [ --locale locale ] [ --months ] [
-ne ] [ -nh ] [ --noedge ] [ --noheader ] [ --output file ] [ -ru ] [ --rateunit ] [ --style number ] [
--summary ] [ --top10 ] [ --transparent ] [ --version ] [ -vs ] [ --vsummary ]
```

DESCRIPTION

The purpose of **vnstati** is to provide image output support for statistics collected using **vnstat**(1). The image file format is limited to png. All basic outputs of vnStat are supported excluding live traffic features. The image can be outputted either to a file or to standard output.

OPTIONS

-c, --cache time

Update output file only if at least *time* minutes have passed since the previous file update. This option is ignored if stdout is used as output.

--config file

Use *file* as config file instead of using normal config file search function.

-d, --days

Output traffic for days.

--dbdir directory

Use *directory* as database directory instead of using the directory specified in the configuration file or the hardcoded default if no configuration file is available.

-h, --hours

Output traffic for the last 24 hours.

-hs, --hsummary

Output traffic summary including hourly data using a horizontal layout.

-i, --iface interface

Use interface instead of default or configured interface.

--locale locale

Use *locale* instead of using the locale setting specified in the configuration file or the system default if no configuration file is available.

-m, --months

Output traffic for months.

-ne, --noedge

Remove darker edges from around the image.

-nh, --noheader

Remove header containing title and update time. Time of the previous update will still be visible in the lower right corner using a less visible color.

-o, --output file

Write png image to *file* and exit. Output can be directed to stdout by giving "-" as filename.

-ru, --rateunit

Swap the configured rate unit. If rate has been configured to be shown in bytes then rate will be shown in bits if this option is present. In the same way, if rate has been configured to be shown in bits then rate will be shown in bytes when this option is present. Alternatively 0 or 1 can be given as parameter for this option in order to select between bytes (0) and bits (1) regardless of the configuration file setting.

--style number

Modify the content and style of outputs. Setting *number* to 3 will show average traffic rate in all outputs where it is supported. Other values will show bar graphics instead.

-s, --summary

Output traffic summary.

-t, --top10

Output all time top10 traffic days.

--transparent

Toggle background color transparency depending of the TransparentBg setting in the configuration file. Alternatively 0 or 1 can be given as parameter for this option in order to either disable (0) or enable (1) transparency regardless of the configuration file setting.

-v, --version

Show current version.

-vs, --vsummary

Output traffic summary including hourly data using a vertical layout.

-?, --help

Show a command summary.

FILES

/var/lib/vnstat/

Default database directory. Files are named according to the monitored interfaces.

/etc/vnstat.conf

Config file that will be used unless \$HOME/.vnstatrc exists. See **vnstat.conf**(5) for more information.

EXAMPLES

vnstati -s -i eth0 -o /tmp/vnstat.png

Output traffic summary for interface eth0 to file /tmp/vnstat.png.

vnstati -vs -i eth0+eth1+eth2 -o /tmp/vnstat.png

Output traffic summary with hourly data under the normal summary for a merge of interfaces eth0, eth1 and eth2 to file /tmp/vnstat.png.

vnstati -h -c 15 -o /tmp/vnstat_h.png

Output hourly traffic statistics for default interface to file /tmp/vnstat_h.png if the file has not been updated within the last 15 minutes.

vnstati -d -ne -nh -o -

Output daily traffic statistics without displaying the header section and edges for default interface to standard output (stdout).

vnstati -m --config /home/me/vnstat.cfg -i -o -

Output monthly traffic statistics for default interface specified in configuration file /home/me/vn-stat.cfg to standard output (stdout).

AUTHOR

Teemu Toivola <tst at iki dot fi>

SEE ALSO

vnstat(1), vnstatd(1), vnstat.conf(5), units(7)